

## Credentialing Software



### **Installation - Network Version for Simultaneous Users**

To install the Network Version of the Credentialing Software, the following items are needed/recommended:

#### **The Database Host (On a Windows Server):**

- Windows NT 4.0 or Windows 2000 Server (with the latest service packs).
- To get the best performance, SCSI hard drives are preferred over IDE or ATA.
- Internet Explorer version 5.0 or later.
- Microsoft Management Console to manage the FileMaker Server Service.
- A CD drive.
- FileMaker Server 5.5 software.
- A network card installed and properly configured for the network.
- TCP/IP or IPX networking protocols.
- A static IP address for the database host.
- Administrator access.

#### **On a Windows Workstation:**

In addition to the items listed above, the following are needed:

- A Windows NT 4.0 Workstation (with SP4 or higher) or a Windows 2000 Professional Workstation may be used for smaller networking installations.
- The Workstation host should be dedicated to hosting this application only. It should not be used for any other tasks.

#### **For The Network:**

- 10base-T is acceptable, but 100base-T or 1000base-T is preferable.
- All network connections should be tested prior to installation and accessible to the database host.
- Internet access for downloads of software updates and new form orders.
- An email account for the individual responsible for installing the updates and/or tech support questions.

#### **For Windows Client:**

- Windows 95, 98, ME, NT 4.0 Workstation (SP4 or above), 2000 Professional, or Windows XP Professional.
- FileMaker Workstation 5.5 software (requires a unique serial number for each PC on the network).
- A CD drive must be available to each PC.
- A network card installed and properly configured for the network with TCP/IP or IPX networking.
- Administrator access to the workstations (NT 4.0 or 2000).

#### **For Printing:**

- A printer attached to the computer or available through the network. The drivers should be installed and tested prior to the installation.
- The printer should be a laser printer with at least 16 MB RAM.

***For Linux or Mac, contact Wybtrak today for specifics.***

***Make it Simple. Make it Wybtrak.***

***Contact Wybtrak to arrange for a free demonstration.***

**For more information, please contact:**

**Troy Johns**

1.877.992.8725 (toll-free)  
702.382.5858 x230 (office)

[troyj@wybtrak.com](mailto:troyj@wybtrak.com)  
[www.wybtrak.com](http://www.wybtrak.com)